Package 'JDCruncheR'

April 15, 2025

Type Package

Title Interface Between the 'JDemetra+' Cruncher and R, and Quality Report Generator

Version 0.3.5

Description Tool for generating quality reports from cruncher outputs (and calculating series scores). The latest version of the cruncher can be downloaded here:

<https://github.com/jdemetra/jwsacruncher/releases>.

License EUPL

URL https://github.com/InseeFr/JDCruncheR,

https://inseefr.github.io/JDCruncheR/

BugReports https://github.com/InseeFr/JDCruncheR/issues

Depends R (>= 4.1)

Imports openxlsx, stats, tools, utils

Suggests testthat (>= 3.0.0)

Config/testthat/edition 3

Encoding UTF-8

RoxygenNote 7.3.2

NeedsCompilation no

Author Tanguy Barthelemy [aut, cre, art],

Alain Quartier-la-Tente [aut] (<https://orcid.org/0000-0001-7890-3857>), Institut national de la statistique et des études économiques [cph] (https://www.insee.fr/), Anna Smyk [aut]

Maintainer Tanguy Barthelemy <tanguy.barthelemy@insee.fr>

Repository CRAN

Date/Publication 2025-04-15 09:10:02 UTC

Contents

add_indicator	2
compute_score	3
export_xlsx	5
export_xlsx.mQR_matrix	6
export_xlsx.QR_matrix	7
extract_QR	8
extract_score	9
get_thresholds	11
print.QR_matrix	11
QR_matrix	12
QR_var_manipulation	13
rbind.QR_matrix	14
recode_indicator_num	
set_thresholds	
sort	17
weighted_score	18
	20

Index

add_indicator Adding an indicator in QR_matrix objects

Description

Function to add indicators in QR_matrix objects.

Usage

```
add_indicator(x, indicator, variable_name, ...)
```

Arguments

х	a QR_matrix or mQR_matrix object
indicator	a vector or a data.frame (cf. details).
variable_name	a string containing the name of the variables to add.
	other parameters of the function merge.

Details

The function add_indicator() adds the chosen indicator to the values matrix of a quality report. Therefore, because said indicator isn't added in the modalities matrix, it cannot be used to calculate a score (except for weighting). Before using the added variable for score calculation, it will have to be coded with the function recode_indicator_num.

The new indicator can be a vector or a data.frame. In both cases, its format must allow for pairing:

compute_score

- a vector's elements must be named and these names must match those of the quality report (variable "series");
- a data. frame must contain a "series" column that matches with the quality report's series.

Value

This function returns the same object, enhanced with the chosen indicator. So if the input x is a QR_matrix, an object of class QR_matrix is returned. If the input x is a mQR_matrix, an object of class mQR_matrix is returned.

See Also

Traduction française

Other var QR_matrix manipulation: QR_var_manipulation, recode_indicator_num()

compute_score Score calculation

Description

To calculate a score for each series from a quality report

Usage

```
## S3 method for class 'QR_matrix'
compute_score(
  х,
  score_pond = c(qs_residual_sa_on_sa = 30L, f_residual_sa_on_sa = 30L,
  qs_residual_sa_on_i = 20L, f_residual_sa_on_i = 20L, f_residual_td_on_sa = 30L,
  f_residual_td_on_i = 20L, oos_mean = 15L, oos_mse = 10L, residuals_independency =
  15L, residuals_homoskedasticity = 5L, residuals_skewness = 5L, m7 = 5L, q_m2 = 5L),
 modalities = c("Good", "Uncertain", "", "Bad", "Severe"),
  normalize_score_value,
  na.rm = TRUE,
 n_contrib_score,
  conditional_indicator = NULL,
  thresholds = getOption("jdc_thresholds"),
)
## S3 method for class 'mQR_matrix'
compute_score(x, ...)
```

x	a QR_matrix or mQR_matrix object.	
score_pond	the formula used to calculate the series score.	
modalities	modalities ordered by importance in the score calculation (cf. details).	
normalize_scor	e_value	
	integer indicating the reference value for weights normalisation. If missing, weights will not be normalised.	
na.rm	logical indicating whether missing values must be ignored when calculating the score.	
n_contrib_scor	e	
	integer indicating the number of variables to create in the quality report's values matrix to store the n_contrib_score greatest contributions to the score (cf. details). If not specified, no variable is created.	
conditional_indicator		
	a list containing 3-elements sub-lists: "indicator", "conditions" and "condi- tion_modalities". To reduce down to 1 the weight of chosen indicators depend- ing on other variables' values (cf. details).	
thresholds	list of numerical vectors. Thresholds applied to the various tests in order to classify into modalities Good, Uncertain, Bad and Severe. By default, the value of the "jdc_threshold" option is used. You can call the get_thresholds function to see what the thresholds object should look like.	
	other unused parameters.	

Details

The function compute_score calculates a score from the modalities of a quality report: to each modality corresponds a weight that depends on the parameter modalities. The default parameter is c("Good", "Uncertain", "Bad", "Severe"), and the associated weights are respectively 0, 1, 2 and 3.

The score calculation is based on the score_pond parameter, which is a named integer vector containing the weights to apply to the (modalities matrix) variables. For example, with score_pond = c(qs_residual_sa_on_sa = 10, f_residual_td_on_sa = 5), the score will be based on the variables qs_residual_sa_on_sa and f_residual_td_on_sa. The qs_residual_sa_on_sa grades will be multiplied by 10 and the f_residual_td_on_sa grades, by 5. To ignore the missing values when calculating a score, use the parameter na.rm = TRUE.

The parameter normalize_score_value can be used to normalise the scores. For example, to have all scores between 0 and 20, specify normalize_score_value = 20.

When using parameter n_contrib_score, n_contrib_score new variables are added to the quality report's values matrix. These new variables store the names of the variables that contribute the most to the series score. For example, n_contrib_score = 3 will add to the values matrix the three variables that contribute the most to the score. The new variables' names are $i_{\rm highest_score}$, with i being the rank in terms of contribution to the score (1_highest_score contains the name of the greatest contribution, 2_highest_score the second greatest, etc). Only the variables that have a non-zero contribution to the score is 0, all $i_{\rm highest_score}$ variables will be empty. And if a series score is positive only because of the m7 statistic, 1_highest_score will have a value of "m7" for this series and the other $i_{\rm highest_score}$ will be empty.

Some indicators are only relevant under certain conditions. For example, the homoscedasticity test is only valid when the residuals are independant, and the normality tests, only when the residuals are both independant and homoscedastic. In these cases, the parameter conditional_indicator can be of use since it reduces the weight of some variables down to 1 when some conditions are met. conditional_indicator is a list of 3-elements sub-lists:

- "indicator": the variable whose weight will be conditionally changed
- "conditions": the variables used to define the conditions
- "conditions_modalities": modalities that must be verified to induce the weight change For example, conditional_indicator = list(list(indicator = "residuals_skewness", conditions = c("residuals_independency", "residuals_homoskedasticity"), conditions_modalities = c("Bad", "Severe"))), reduces down to 1 the weight of the variable "residuals_skewness" when the modalities of the independancy test ("residuals_independency") or the homoscedasticity test ("residuals_homoskedasticity") are "Bad" or "Severe".

Value

a QR_matrix or mQR_matrix object.

See Also

Traduction française

Examples

```
# Path of matrix demetra_m
demetra_path <- file.path(
    system.file("extdata", package = "JDCruncheR"),
    "WS/ws_ipi/Output/SAProcessing-1",
    "demetra_m.csv"
)
# Extract the quality report from the demetra_m file
QR <- extract_QR(demetra_path)
# Calculer le score
QR <- compute_score(QR, n_contrib_score = 2)
print(QR)
# Extract the modalities matrix:
QR[["modalities"]][["score"]]
```

export_xlsx

Exporting QR_matrix or mQR_matrix objects in an Excel file

Description

Exporting QR_matrix or mQR_matrix objects in an Excel file

Usage

export_xlsx(x, ...)

Arguments

Х	a QR_matrix or mQR_matrix object.
	other parameters of the function <code>export_xlsx.QR_matrix</code> .

Value

If x is a mQR_matrix, the function returns invisibly (via invisible(x)) the same mQR_matrix object as x. Else if x is a QR_matrix, the function returns invisibly (via invisible(x)) a workbook object created by XLConnect::loadWorkbook() for further manipulation.

See Also

Other QR_matrix functions: export_xlsx.QR_matrix(), export_xlsx.mQR_matrix(), extract_QR(), rbind.QR_matrix(), sort(), weighted_score()

export_xlsx.mQR_matrix

Exporting mQR_matrix objects in Excel files

Description

To export several quality reports in Excel files

Usage

```
## S3 method for class 'mQR_matrix'
export_xlsx(
    x,
    export_dir,
    layout_file = c("ByComponent", "ByQRMatrix", "AllTogether"),
    auto_format = TRUE,
    overwrite = TRUE,
    ...
)
```

Arguments

x	a mQR_matrix object to export.
export_dir	export directory.
layout_file	export parameter. By default, (layout_file = "ByComponent") and an Excel file is exported for each part of the quality report matrix (modalities and values matrices). To group both modalities and values reports/sheets into a single Excel file, use the option layout_file = "ByQRMatrix".

auto_format	logical indicating whether to format the output (auto_format = TRUE by de-fault).
overwrite	logical indicating whether to create an Excel file if it doesn't exist yet (create = TRUE by default)
	other unused arguments

Value

Returns invisibly (via invisible(x)) the same mQR_matrix object as x.

See Also

Traduction française

Other QR_matrix functions: export_xlsx(), export_xlsx.QR_matrix(), extract_QR(), rbind.QR_matrix(), sort(), weighted_score()

export_xlsx.QR_matrix Exporting QR_matrix objects in an Excel file

Description

To export a quality report in an Excel file.

Usage

```
## S3 method for class 'QR_matrix'
export_xlsx(x, file, auto_format = TRUE, overwrite = TRUE, ...)
```

Arguments

Х	a QR_matrix object.
file	a character object with the path to the file to export que l'on veut créer
auto_format	logical indicating whether to format the output (auto_format = TRUE by default).
overwrite	logical indicating whether to create an Excel file if it doesn't exist yet (create = TRUE by default)
	other unused arguments

Value

Returns invisibly (via invisible(x)) a workbook object created by XLConnect::loadWorkbook() for further manipulation.

See Also

Traduction française

Other QR_matrix functions: export_xlsx(), export_xlsx.mQR_matrix(), extract_QR(), rbind.QR_matrix(), sort(), weighted_score() extract_QR

Description

To extract a quality report from the csv file containing the diagnostics matrix.

Usage

```
extract_QR(
   file,
   x,
   matrix_output_file,
   sep = ";",
   dec = ",",
   thresholds = getOption("jdc_thresholds")
)
```

Arguments

file	the csv file containing the diagnostics matrix. This argument supersedes the argument matrix_output_file.	
х	data.frame containing the diagnostics matrix.	
matrix_output_file		
	the csv file containing the diagnostics matrix.	
sep	the separator used in the csv file (by default, sep = ";")	
dec	the decimal separator used in the csv file (by default, dec = ", ")	
thresholds	list of numerical vectors. Thresholds applied to the various tests in order to classify into modalities Good, Uncertain, Bad and Severe. By default, the value of the "jdc_threshold" option is used. You can call the get_thresholds function to see what the thresholds object should look like.	

Details

This function generates a quality report from a csv file containing diagnostics (usually from the file *demetra_m.csv*). The *demetra_m.csv* file can be generated by launching the cruncher (functions cruncher or cruncher_and_param) with the default export parameters, having used the default option csv_layout = "vtable" to format the output tables of the functions cruncher_and_param and create_param_file when creating the parameters file.

This function returns a QR_matrix object, which is a list of 3 objects:

- modalities, a data.frame containing several indicators and their categorical quality (Good, Uncertain, Bad, Severe).
- values, a data.frame containing the same indicators and the values that lead to their quality category (i.e.: p-values, statistics, etc.) as well as additional variables that don't have a modality/quality (series frequency and arima model).

extract_score

• score_formula that will store the formula used to calculate the score (when relevant). Its initial value is NULL.

If x is supplied, the file and matrix_output_file arguments are ignored. The file argument also designates the path to the file containing the diagnostic matrix (which can be imported into R in parallel and used with the x argument).

Value

a QR_matrix object.

See Also

Traduction française

```
Other QR_matrix functions: export_xlsx(), export_xlsx.QR_matrix(), export_xlsx.mQR_matrix(),
rbind.QR_matrix(), sort(), weighted_score()
```

Examples

```
# Path of matrix demetra_m
demetra_path <- file.path(
    system.file("extdata", package = "JDCruncheR"),
    "WS/ws_ipi/Output/SAProcessing-1",
    "demetra_m.csv"
)
# Extract the quality report from the demetra_m file
QR <- extract_QR(file = demetra_path)
print(QR)
# Extract the modalities matrix:
QR[["modalities"]]
# Or:
QR[["modalities"]]</pre>
```

extract_score Score extraction

Description

To extract score variables from QR_matrix or mQR_matrix objects.

Usage

```
extract_score(
    x,
    format_output = c("data.frame", "vector"),
    weighted_score = FALSE
)
```

х	a QR_matrix or mQR_matrix.
format_output	string of characters indicating the output format: either a data.frame or a vector.
weighted_score	logical indicating whether to extract the weighted score (if previously calculated) or the unweighted one. By default, the unweighted score is extracted.

Details

For QR_matrix objects, the output is a vector or the object NULL if no score was previously calculated. For mQR_matrix objects, it is a list of scores (NULL elements or vectors).

Value

extract_score() returns a data.frame with two column: the series name and their score.

See Also

Traduction française

Examples

```
# Path of matrix demetra_m
demetra_path <- file.path(</pre>
    system.file("extdata", package = "JDCruncheR"),
    "WS/ws_ipi/Output/SAProcessing-1",
    "demetra_m.csv"
)
# Extract the quality report from the demetra_m file
QR <- extract_QR(demetra_path)</pre>
# Compute the score
QR1 <- compute_score(x = QR, n_contrib_score = 5)</pre>
QR2 <- compute_score(
    x = QR,
    score_pond = c(qs_residual_sa_on_sa = 5, qs_residual_sa_on_i = 30,
                    f_residual_td_on_sa = 10, f_residual_td_on_i = 40,
                    oos_mean = 30, residuals_skewness = 15, m7 = 25)
)
mQR <- mQR_matrix(list(a = QR1, b = QR2))</pre>
# Extract score
extract_score(QR1)
extract_score(mQR)
```

get_thresholds Get all (default) thresholds

Description

Get all (default) thresholds

Usage

get_thresholds(test_name, default = TRUE)

Arguments

test_name	String. The name of the test to get.
default	Boolean. (default is TRUE) If TRUE, the default threshold will be returned. If
	FALSE the current used thresholds.

Details

If test_name is missing, all threshold will be returned.

Examples

```
# Get all default thresholds
get_thresholds(default = TRUE)
# Get all current thresholds
get_thresholds(default = FALSE)
# Get all current thresholds
get_thresholds(test_name = "oos_mean", default = FALSE)
```

print.QR_matrix Printing QR_matrix and mQR_matrix objects

Description

To print information on a QR_matrix or mQR_matrix object.

Usage

```
## S3 method for class 'QR_matrix'
print(x, print_variables = TRUE, print_score_formula = TRUE, ...)
## S3 method for class 'mQR_matrix'
print(x, score_statistics = TRUE, ...)
```

х	a mQR_matrix or mQR_matrix object.	
print_variables		
	logical indicating whether to print the indicators' name (including additionnal variables).	
print_score_formula		
	logical indicating whether to print the formula with which the score was calculated (when calculated).	
	other unused arguments.	
score_statistics		
	logical indicating whether to print the statistics in the mQR_matrix scores (when calculated).	

Value

the print method prints a mQR_matrix or mQR_matrix object and returns it invisibly (via invisible(x)).

See Also

Traduction française

Description

mQR_matrix() and QR_matrix() are creating one (or several) quality report. The function is.QR_matrix() and is.mQR_matrix() are functions to test whether an object is a quality report or a list of quality reports.

Usage

```
QR_matrix(modalities = NULL, values = NULL, score_formula = NULL)
```

Quality report objects

```
mQR_matrix(x = list(), ...)
```

is.QR_matrix(x)

is.mQR_matrix(x)

Arguments

modalities	a data.frame containing the output variables' modalities (Good, Bad, etc.)
values	a data.frame containing the output variables' values (test p-values, test statis-
	tics, etc.) Therefore, the values data frame can contain more variables than the
	data frame modalities.

<pre>score_formula</pre>	the formula used to calculate the series score (if defined).
x	a QR_matrix object, a mQR_matrix object or a list of QR_matrix objects.
	objects of the same type as x.

Details

AQR_matrix object is a list of three items:

- modalities, a data.frame containing a set of categorical variables (by default: Good, Uncertain, Bad, Severe).
- values, a data.frame containing the values corresponding to the modalities indicators (i.e. p-values, statistics, etc.), as well as variables for which a modality cannot be defined (e.g. the series frequency, the ARIMA model, etc).
- score_formula contains the formula used to calculate the series score (once the calculus is done).

Value

QR_matrix() creates and returns a QR_matrix object. mQR_matrix() creates and returns a mQR_matrix object (ie. a list of QR_matrix objects). is.QR_matrix() and is.mQR_matrix() return Boolean values (TRUE or FALSE).

See Also

Traduction française

QR_var_manipulation Editing the indicators list

Description

Functions to remove indicators (remove_indicators()) or retrain some indicators only (retain_indicators()) from QR_matrix or mQR_matrix objects. The series names (column "series") cannot be removed.

Usage

```
remove_indicators(x, ...)
```

retain_indicators(x, ...)

Arguments

Х	a QR_matrix or mQR_matrix object.
	names of the variable to remove (or keep)

Value

remove_indicators() returns the same object x reduced by the flags and variables used as arguments ... So if the input x is a QR_matrix, an object of class QR_matrix is returned. If the input x is a mQR_matrix, an object of class mQR_matrix is returned.

See Also

Traduction française

Other var QR_matrix manipulation: add_indicator(), recode_indicator_num()

Examples

```
# Path of matrix demetra_m
demetra_path <- file.path(</pre>
    system.file("extdata", package = "JDCruncheR"),
    "WS/ws_ipi/Output/SAProcessing-1",
    "demetra_m.csv"
)
# Extract the quality report from the demetra_m file
QR <- extract_QR(demetra_path)</pre>
# Compute the score
QR <- compute_score(QR, n_contrib_score = 2)
# Retain indicators
retain_indicators(QR, "score", "m7") # retaining "score" and "m7"
retain_indicators(QR, c("score", "m7")) # Same
# Remove indicators
QR <- remove_indicators(QR, "score") # removing "score"</pre>
extract_score(QR) # is NULL because we removed the score indicator
```

rbind.QR_matrix Combining QR_matrix objects

Description

Function to combine multiple QR_matrix objects: line by line, both for the modalities and the values table.

Usage

```
## S3 method for class 'QR_matrix'
rbind(..., check_formula = TRUE)
```

. . .

QR_matrix objects to combine.

check_formula logical indicating whether to check the score formulas' coherency. By default, check_formula = TRUE: an error is returned if the scores were calculated with different formulas. If check_formula = FALSE, no check is performed and the score_formula of the output is NULL.

Value

rbind.QR_matrix() returns a QR_matrix object.

See Also

Traduction française

```
Other QR_matrix functions: export_xlsx(), export_xlsx.QR_matrix(), export_xlsx.mQR_matrix(), extract_QR(), sort(), weighted_score()
```

Examples

```
# Path of matrix demetra_m
demetra_path <- file.path(
    system.file("extdata", package = "JDCruncheR"),
    "WS/ws_ipi/Output/SAProcessing-1",
    "demetra_m.csv"
)
# Extract the quality report from the demetra_m file
QR <- extract_QR(demetra_path)
# Compute differents scores
QR1 <- compute_score(QR, score_pond = c(m7 = 2, q = 3, qs_residual_sa_on_sa = 5))
QR2 <- compute_score(QR, score_pond = c(m7 = 2, qs_residual_sa_on_sa = 5))
# Merge two quality report
try(rbind(QR1, QR2)) # Une erreur est renvoyée
rbind(QR1, QR2, check_formula = FALSE)
```

recode_indicator_num Converting "values variables" into "modalities variables"

Description

To transform variables from the values matrix into categorical variables that can be added into the modalities matrix.

Usage

```
recode_indicator_num(
 х,
 variable_name,
 breaks = c(0, 0.01, 0.05, 0.1, 1),
 labels = c("Good", "Uncertain", "Bad", "Severe"),
  . . .
)
```

Arguments

a QR_matrix or mQR_matrix object.
a vector of strings containing the names of the variables to convert.
see function cut.
see function cut.
other parameters of the cut function.

Value

The function recode_indicator_num() returns the same object, enhanced with the chosen indicator. So if the input x is a QR_matrix, an object of class QR_matrix is returned. If the input x is a mQR_matrix, an object of class mQR_matrix is returned.

See Also

Traduction française

Other var QR_matrix manipulation: QR_var_manipulation, add_indicator()

set_thresholds Set values for thresholds

Description

Set values for thresholds

Usage

set_thresholds(test_name, thresholds)

Arguments

test_name	String. The name of the test to update.
thresholds	Named vector of numerics. The upper values of each break of a threshold.

sort

Details

If test_name is missing, the argument thresholds is not used and all thresholds will be updated to their default values.

If test_name is not missing, but if the argument thresholds is missing then only the thresholds of the test test_name will be updated to its default values.

Finally, if test_name and thresholds are not missing, then only the thresholds of the test test_name are updated with the value thresholds.

Examples

```
# Set "m7"
set_thresholds(
    test_name = "m7",
    thresholds = c(Good = 0.8, Bad = 1.4, Severe = Inf)
)
# Set "oos_mean" to default
set_thresholds(test_name = "oos_mean")
# Set all thresholds to default
set_thresholds()
```

sort

QR_matrix and mQR_matrix sorting

Description

To sort the quality reports on one or several variables

Usage

```
## S3 method for class 'QR_matrix'
sort(x, decreasing = FALSE, sort_variables = "score", ...)
## S3 method for class 'mQR_matrix'
sort(x, decreasing = FALSE, sort_variables = "score", ...)
```

Arguments

х	a QR_matrix or mQR_matrix object
decreasing	logical indicating whether the quality reports must be sorted in ascending or decreasing order. By default, the sorting is done in ascending order.
<pre>sort_variables</pre>	They must be present in the modalities table.
	other parameters of the function order (unused for now)

Value

the input with sorted quality reports

See Also

Traduction française

```
Other QR_matrix functions: export_xlsx(), export_xlsx.QR_matrix(), export_xlsx.mQR_matrix(),
extract_QR(), rbind.QR_matrix(), weighted_score()
```

Examples

```
# Path of matrix demetra_m
demetra_path <- file.path(
    system.file("extdata", package = "JDCruncheR"),
    "WS/ws_ipi/Output/SAProcessing-1",
    "demetra_m.csv"
)
# Extract the quality report from the demetra_m file
QR <- extract_QR(demetra_path)
# Compute the score
QR <- compute_score(QR, n_contrib_score = 2)
print(QR[["modalities"]][["score"]])
# Sort the scores
# To sort by ascending scores
QR <- sort(QR, sort_variables = "score")
print(QR[["modalities"]][["score"]])
```

weighted_score Weighted score calculation

Description

Function to weight a pre-calculated score

Usage

weighted_score(x, pond = 1L)

Arguments

Х	a QR_matrix or mQR_matrix object
pond	the weights to use. Can be an integer, a vector of integers, the name of one of
	the quality report variables or a list of weights for the mQR_matrix objects.

weighted_score

Value

the input with an additionnal weighted score

See Also

Traduction française

```
Other QR_matrix functions: export_xlsx(), export_xlsx.QR_matrix(), export_xlsx.mQR_matrix(),
extract_QR(), rbind.QR_matrix(), sort()
```

Examples

```
# Path of matrix demetra_m
demetra_path <- file.path(
    system.file("extdata", package = "JDCruncheR"),
    "WS/ws_ipi/Output/SAProcessing-1",
    "demetra_m.csv"
)
# Extract the quality report from the demetra_m file
QR <- extract_QR(demetra_path)
# Compute the score</pre>
```

```
QR <- compute_score(QR, n_contrib_score = 2)</pre>
```

```
# Weighted score
QR <- weighted_score(QR, 2)
print(QR)</pre>
```

```
# Extract the weighted score
QR[["modalities"]][["score_pond"]]
```

Index

* QR_matrix functions export_xlsx, 5 export_xlsx.mQR_matrix,6 export_xlsx.QR_matrix,7 extract_QR, 8 rbind.QR_matrix, 14 sort, 17 weighted_score, 18 * var QR_matrix manipulation add_indicator, 2 QR_var_manipulation, 13 recode_indicator_num, 15 add_indicator, 2, 14, 16 compute_score, 3 create_param_file, 8 cruncher, 8cruncher_and_param, 8 cut, 16 export_xlsx, 5, 7, 9, 15, 18, 19 export_xlsx.mQR_matrix, 6, 6, 7, 9, 15, 18, 19 export_xlsx.QR_matrix, 6, 7, 7, 9, 15, 18, 19 extract_QR, 6, 7, 8, 15, 18, 19 extract_score, 9 get_thresholds, 4, 8, 11 is.mQR_matrix(QR_matrix), 12 is.QR_matrix(QR_matrix), 12 merge, 2 mQR_matrix, 2, 4-7, 9, 10, 12, 13, 16-18 mQR_matrix (QR_matrix), 12 order, *17* print.mQR_matrix (print.QR_matrix), 11

print.QR_matrix, 11

QR_matrix, 2, 4-10, 12, 13-18 QR_var_manipulation, 3, 13, 16 rbind.QR_matrix, 6, 7, 9, 14, 18, 19 recode_indicator_num, 2, 3, 14, 15 remove_indicators (QR_var_manipulation), 13 retain_indicators (QR_var_manipulation), 13 set_thresholds, 16 sort, 6, 7, 9, 15, 17, 19 Traduction française, 3, 5, 7, 9, 10, 12-16, 18, 19 weighted_score, 6, 7, 9, 15, 18, 18